



This is part of **Family API** which allow to create dual-os version of program runs under OS/2 and DOS

**Note:** This is legacy API call. It is recommended to use 32-bit equivalent

2021/09/17 04:47 · prokushev · [0 Comments](#)

2021/08/20 03:18 · prokushev · [0 Comments](#)

## MouSetPtrShape

This call allows a process to set the pointer shape and size to be used as the mouse device driver pointer image for all applications in a session.

### Syntax

```
MouSetPtrShape (PtrBuffer, PtrDefRec, DeviceHandle)
```

### Parameters

- **PtrBuffer** (PBYTE) - input: Address of a buffer containing the bit image used by the mouse device driver as the pointer shape for that session. The buffer consists of AND and XOR pointer masks in a format meaningful to the pointer draw device driver.

For CGA compatible text modes (0, 1, 2, and 3) the following describes the AND and XOR pointer mask bit definitions for each character cell of the masks. Bit values are:

Bit	Description
15	Blinking
14-12	Background colour
11	Intensity
10-8	Foreground colour
7-0	Character

- **PtrDefRec** (PPTRSHAPE) - input: Address of the structure where the application stores the necessary data for the pointer draw device driver to build a row-by-column image for each bit plane for the current display mode.

**Programming Note:** For other custom displays and for the extended modes of the EGA attachment, it is possible to set the display to modes that require multiple bit planes. In these cases, the area sized by the row and column limits must be repeated for each bit plane supported in that mode. Consequently, the calling process must supply enough data to allow the mouse device driver to draw the pointer shape on all currently supported bit planes in that session. For text modes, row and column offset must equal 0.

- DeviceHandle (HMOU) - input: Contains the handle of the mouse device obtained from a previous MouOpen.

## Return Code

rc (USHORT) - return:Return code descriptions are:

- 0 NO\_ERROR
- 385 ERROR\_MOUSE\_NO\_DEVICE
- 387 ERROR\_MOUSE\_INV\_PARMS
- 466 ERROR\_MOU\_DETACHED
- 501 ERROR\_MOUSE\_NO\_CONSOLE
- 505 ERROR\_MOU\_EXTENDED\_SG

## Remarks

An application passes a data image to the mouse device driver that the mouse driver applies to the screen whenever the logical pointer position is not located in the application-defined collision area. The application synchronizes use of the screen with the mouse driver by way of MouRemovePtr and MouDrawPtr.

The pointer shape is dependent on the display device driver used to support the display device. OS/2 supports text and graphics modes. These modes are restricted to modes 0 through 7, depending on the display device. Character modes (modes 0, 1, 2, 3, and 7) support the pointer cursor only as a reverse block character. This reverse block character has a character height and width equal to 1.

The pointer shape is mapped by the Pointer Draw Device Driver and determined completely by the application. The height and width may vary from 1 through the pel size of the display screen. For restrictions concerning the Pointer Draw Device Driver, see IBM Operating System/2 Version 1.2 I/O Subsystems And Device Support Volume 1.

## Bindings

### C

```
typedef struct _PTRSHAPE { /* moups */
    USHORT cb;           /* total length necessary to build image */
    USHORT col;          /* # of columns in mouse shape */
    USHORT row;          /* number of rows in mouse shape */
    USHORT colHot;       /* column coordinate of pointer image hotspot */
    USHORT rowHot;       /* row coordinate of pointer image hotspot */
} PTRSHAPE;

#define INCL_MOU
```

```

USHORT  rc = MouSetPtrShape(PtrBuffer, PtrDefRec, DeviceHandle);

PBYTE    PtrBuffer;      /* Pointer shape buffer */
PPTRSHAPE PtrDefRec;    /* Pointer definition record */
HMOU     DeviceHandle;  /* Mouse device handle */

USHORT  rc;             /* return code */

```

## MASM

```

PTRSHAPE  struct
  mounds_cb      dw  ? ;total length necessary to build image
  mounds_col     dw  ? ;# of columns in mouse shape
  mounds_row     dw  ? ;number of rows in mouse shape
  mounds_colHot  dw  ? ;column coordinate of pointer image hotspot
  mounds_rowHot  dw  ? ;row coordinate of pointer image hotspot
PTRSHAPE ends

EXTRN  MouSetPtrShape:FAR
INCL_MOU          EQU 1

PUSH@ OTHER  PtrBuffer      ;Pointer shape buffer
PUSH@ OTHER  PtrDefRec     ;Pointer definition record
PUSH  WORD   DeviceHandle  ;Mouse device handle
CALL   MouSetPtrShape

```

Returns WORD

From:  
<http://osfree.ru/doku/> - osFree wiki



Permanent link:  
<http://osfree.ru/doku/doku.php?id=en:docs:fapi:mousetptrshape&rev=1634262807>

Last update: 2021/10/15 01:53