

## MouInitReal

**Bindings:** C, MASM

This call initializes mouse pointer draw support for DOS mode.

*MouInitReal* (DriverName)

*DriverName* (**PSZ**) - input Address of the name of the Pointer Draw Device Driver used as the pointer-image drawing routine for the DOS mode session.

The name of the device driver must be included in the CONFIG.SYS file at system start-up time.

If the selector portion of the far address is zero and the offset portion is non-zero, the offset portion identifies the power-up display configuration.

*rc* (**USHORT**) - return Return code descriptions are:

0	NO_ERROR
385	ERROR_MOUSE_NO_DEVICE
466	ERROR_MOU_DETACHED
412	ERROR_MOUSE_SMG_ONLY
501	ERROR_MOUSE_NO_CONSOLE
505	ERROR_MOU_EXTENDED_SG

### Remarks

[MouInitReal](#) is issued by the Base Video Subsystem at system initialization time.

The DOS mode mouse API (INT 33H), in contrast to the OS/2 mode Mouse API, does not contain an OPEN command. In addition, there is only one session for DOS mode.

The default pointer draw routine for DOS mode is located in the same pointer draw device driver, POINTER\$, that is used for OS/2 mode. Establishing addressability to the pointer draw routine must be done during system initialization. This requires passing the entry point of the DOS mode pointer draw routine to the mouse device driver. This is the purpose of the [MouInitReal](#) call. It passes the address of the default, power-up pointer draw routine for DOS mode to the mouse device driver. This initialization is transparent to applications.

This call is for use only by the Base Video Subsystem when invoked during system initialization under the shell/session manager PID.

The error code ERROR\_MOUSE\_SMG\_ONLY is valid from shell process only.

### C bindings

```
#define INCL_MOU

USHORT rc = MouInitReal(DriverName);
```

```
PSZ      DriverName;      /* Pointer draw driver name */
USHORT   rc;              /* return code */
```

## MASM bindings

```
EXTRN MouInitReal:FAR
INCL_MOU      EQU 1

PUSH@  ASCIIZ  DriverName      ;Pointer draw driver name
CALL   MouInitReal

Returns WORD
```

From:

<http://osfree.ru/doku/> - **osFree wiki**

Permanent link:

<http://osfree.ru/doku/doku.php?id=en:ibm:prcp:mou:initreal>

Last update: **2016/09/15 04:10**

