 This is part of **Family API** which allow to create dual-os version of program runs under OS/2 and DOS

**Note:** This is legacy API call. It is recommended to use 32-bit equivalent

2021/09/17 04:47 · prokushev · 0 Comments
2021/08/20 03:18 · prokushev · 0 Comments

# DosQFSInfo

This call queries information from a file system device.

#### Syntax

DosQFSInfo (DriveNumber, FSInfoLevel, FSInfoBuf, FSInfoBufSize)

#### Parameters

;DriveNumber (USHORT) - input : Logical drive number (0 = default, 1 = A, and so on). :When a logical drive is specified, the media in the drive is examined (local drive only) and the request is passed to the FSD responsible for managing that media or to the FSD that is attached to the drive. ;FSInfoLevel (USHORT) - input : Level of file information required. ;FSInfoBuf (PBYTE) - output : Address of the storage area where the system returns the requested level of file information. :Level 1 Information :For FSInfoLevel = 1, information is returned in the following structure: ::filesysid (ULONG) - File system ID. ::sectornum (ULONG) - Number of sectors per allocation unit. ::unitnum (ULONG) - Number of allocation units. ::unitavail (ULONG) - Number of allocation units available. ::bytesnum (USHORT) - Number of bytes per sector. :Level 2 Information :For FSInfoLevel = 2, the information is returned in the following format: ::reserved (ULONG) - Reserved ::volumelength (BYTE) - Length of the volume label, not including the null. ::volumelabel (CHAR) - Volume label ASCIIZ string. ;FSInfoBufSize (USHORT) : Length of the buffer.

#### Return Code

rc (USHORT) - return Return code descriptions are: * 0 NO_ERROR * 15 ERROR_INVALID_DRIVE * 111 ERROR_BUFFER_OVERFLOW * 124 ERROR_INVALID_LEVEL * 125 ERROR_NO_VOLUME_LABEL

#### Remarks

Trailing blanks supplied at volume label definition time are not considered to be part of the label and are therefore not returned as valid label data. Volume label is limited to a length of 11 bytes.

Volume Serial Number is a unique 32-bit number used by OS/2 to positively identify its disk/diskette

volumes. The hard error prompts the user for an unmounted removable volume by displaying both the Volume Serial Number (as an 8 digit hexadecimal number) and the Volume Label.

If there is no volume serial number on the disk/diskette, the volume serial number information is returned as binary zeros. If there is no volume label on the disk/diskette, the volume label information is returned as blank spaces. If there is no volume serial number and/or volume label for disk/diskette volumes formatted by DOS 3.X, this information is not displayed by the Hard Error Handler.

#### Example Code

### C Binding

<PRE> typedef struct _FSALLOCATE {

```
  ULONG  idFileSystem;  /* file system ID */
  ULONG  cSectorUnit;   /* number sectors per allocation unit */
  ULONG  cUnit;         /* number of allocation units */
  ULONG  cUnitAvail;    /* available allocation units */
  USHORT cbSector;      /* bytes per sector */
```

} FSALLOCATE;

typedef struct _FDATE { /* fdate */

unsigned day : 5; /* binary day for directory entry */

```
unsigned month : 4;     /* binary month for directory entry */
unsigned year  : 7;     /* binary year for directory entry */
```

} FDATE;

typedef struct _FTIME { /* ftime */

unsigned twosecs : 5; /* binary number of two-second increments */

```
unsigned minutes : 6;   /* binary number of minutes */
unsigned hours   : 5;   /* binary number of hours */
```

} FTIME;

typedef struct _FSINFO { /* fsinf */

```
  FDATE fdateCreation;
  FTIME ftimeCreation;
  VOLUMELABEL vol;
```

} FSINFO;

typedef struct _VOLUMELABEL { /* vol */

```
  BYTE cch;
  CHAR szVolLabel[12];
```

} VOLUMELABEL;

#define INCL_DOSFILEMGR

USHORT rc = DosQFSInfo(DriveNumber, FSInfoLevel, FSInfoBuf, FSInfoBufSize);

USHORT DriveNumber; /* Drive number */ USHORT FSInfoLevel; /* File system data required */ PBYTE FSInfoBuf; /* File system info buffer */ USHORT FSInfoBufSize; /* File system info buffer size */

USHORT rc; /* return code */ </PRE>

#### MASM Binding

<PRE> FSALLOCATE struc

```
  fsalloc_idFileSystem        dd  ?
  fsalloc_cSectorUnit         dd  ?
  fsalloc_cUnit               dd  ?
  fsalloc_cUnitAvail          dd  ?
  fsalloc_cbSector            dw  ?
```

FSALLOCATE ends

EXTRN DosQFSInfo:FAR INCL_DOSFILEMGR EQU 1

PUSH WORD DriveNumber ;Drive number PUSH WORD FSInfoLevel ;File system data required PUSH@ OTHER FSInfoBuf ;File system info buffer (returned) PUSH WORD FSInfoBufSize ;File system info buffer size CALL DosQFSInfo

Returns WORD

</PRE>

# Note

Text based on http://www.edm2.com/index.php/DosQFSInfo

| **Family API** | | |
|---|---|---|
| DOS | Process Manager | DosBeep DosExit DosSleep DosExecPgm |
| | File Manager | DosChDir DosChgFilePtr DosClose DosDelete DosDupHandle DosMkDir DosMove DosQCurDir DosQCurDisk DosSetFileMode DosOpen DosQFileInfo DosRead DosQFileMode DosQFSInfo DosQVerify DosRmDir DosSelectDisk DosFindClose DosFindFirst DosFindNext DosSetFileInfo DosSetVerify DosWrite DosFileLocks DosSetFHandState DosNewSize DosBufReset DosQFHandState DosSetFSinfo DosShutdown |
| | Memory Manager | DosFreeSeg DosSubAlloc DosSubFree DosSubSet DosAllocHuge DosAllocSeg DosReallocHuge DosReallocSeg DosGetHugeShift DosCreateCSAlias |
| | NLS | DosCaseMap DosGetCtryInfo DosGetDBCSEv DosSetCtryCode DosGetCollate DosGetMessage DosInsMessage DosPutMessage |
| | Date and Time | DosSetDateTime DosGetDateTime |
| | Devices | DosDevConfig DosDevIOCtl DosDevIOCtl2 |
| | Signals | DosHoldSignal DosSetSigHandler |
| | Misc | BadDynLink DosGetEnv DosGetMachineMode DosGetVersion DosError DosErrClass DosSetVec |
| KBD | | KbdCharIn KbdFlushBuffer KbdGetStatus KbdSetStatus KbdStringIn KbdPeek |
| VIO | | VioGetBuf VioGetConfig VioGetCurPos VioGetCurType VioGetPhysBuf VioReadCellStr VioReadCharStr VioScrollUp VioScrollDn VioScrollLf VioScrollRt VioScrUnLock VioSetCurPos VioSetCurType VioSetMode VioGetMode VioShowBuf VioWrtCellStr VioWrtCharStr VioWrtCharStrAtt VioWrtNAttr VioWrtNCell VioWrtNChar VioWrtTTY VioScrLock VioPopUp |
| Tools | | BIND |
| Modules | | DOSCALLS.DLL VIOCALLS.DLL KBDCALLS.DLL MSG.DLL |
| Libraries | | API.LIB OS2386.LIB FAPI.LIB DOSCALLS.LIB SUBCALLS.LIB |

2018/08/25 15:05 · prokushev · 0 Comments

From:
https://osfree.ru/doku/ - **osFree wiki**

Permanent link:
**https://osfree.ru/doku/doku.php?id=en:docs:fapi:dosqfsinfo&rev=1629433262**

Last update: **2021/08/20 04:21**