



This is part of **Family API** which allow to create dual-os version of program runs under OS/2 and DOS

Note: This is legacy API call. It is recommended to use 32-bit equivalent

2021/09/17 04:47 · prokushev · [0 Comments](#)

2021/08/20 03:18 · prokushev · [0 Comments](#)

MouSetScaleFact

This call assigns to the current mouse device driver a new pair of 1-word scaling factors.

Syntax

```
MouSetScaleFact (ScaleStruct, DeviceHandle)
```

Parameters

- ScaleStruct ([PSCALEFACT](#)) - input : Address of the control block structure that contains the current row and column coordinate scaling factors.
- DeviceHandle (HMOU) - input : Handle of the mouse device from a previous MouOpen.

Return Code

rc (USHORT) - return:Return code descriptions are:

- 0 NO_ERROR
- 385 ERROR_MOUSE_NO_DEVICE
- 387 ERROR_MOUSE_INV_PARMS
- 466 ERROR_MOU_DETACHED
- 501 ERROR_MOUSE_NO_CONSOLE
- 505 ERROR_MOU_EXTENDED_SG

Remarks

MouSetScaleFact sets the mickey-to-pixel ratio for mouse motion. The row scale and column scale ratios specify a number of mickeys for each 8 pixels. The default value for the row scale is 16 mickeys for each 8 pixels. The default value for the column scale is 8 mickeys to 8 pixels.

The number of pixels moved does not have to correspond 1-to-1 with the number of mickeys the mouse moves. The scaling factor defines a sensitivity for the mouse that is a ratio of the number of

mickeys required to move the cursor 8 pixels on the screen. The sensitivity determines at what rate the cursor moves on the screen.

Bindings

C

```
typedef struct _SCALEFACT { /* mousc */
    USHORT rowScale;        /* row scaling factor */
    USHORT colScale;        /* column coordinate scaling factor */
} SCALEFACT;

#define INCL_MOU

USHORT rc = MouSetScaleFact(ScaleStruct, DeviceHandle);

PSCALEFACT ScaleStruct; /* 2-word structure */
HMOU DeviceHandle; /* Mouse device handle */

USHORT rc; /* return code */
```

MASM

```
SCALEFACT struc
    mousc_rowScale dw ? ;row scaling factor
    mousc_colScale dw ? ;column coordinate scaling factor
SCALEFACT ends

EXTRN MouSetScaleFact:FAR
INCL_MOU EQU 1

PUSH@ OTHER ScaleStruct ;2-word structure
PUSH WORD DeviceHandle ;Mouse device handle
CALL MouSetScaleFact

Returns WORD
```

Family API		
DOS	Process Manager	DosBeep DosExit DosSleep DosExecPgm
	File Manager	DosChDir DosChgFilePtr DosClose DosDelete DosDupHandle DosMkDir DosMove DosQCurDir DosQCurDisk DosSetFileMode DosOpen DosQFileInfo DosRead DosQFileMode DosQFSInfo DosQVerify DosRmdir DosSelectDisk DosFindClose DosFindFirst DosFindNext DosSetFileInfo DosSetVerify DosWrite DosFileLocks DosSetFHandState DosNewSize DosBufReset DosQFHandState DosSetFSinfo DosShutdown
	Memory Manager	DosFreeSeg DosSubAlloc DosSubFree DosSubSet DosAllocHuge DosAllocSeg DosReallocHuge DosReallocSeg DosGetHugeShift DosCreateCSAlias
	NLS	DosCaseMap DosGetCtryInfo DosGetDBCSEv DosSetCtryCode DosGetCollate DosGetMessage DosInsMessage DosPutMessage
	Date and Time	DosSetDateTime DosGetDateTime
	Devices	DosDevConfig DosDevIOct1 DosDevIOct2
	Signals	DosHoldSignal DosSetSigHandler
	Misc	BadDynLink DosGetEnv DosGetMachineMode DosGetVersion DosError DosErrClass DosSetVec
KBD		KbdCharIn KbdFlushBuffer KbdGetStatus KbdSetStatus KbdStringIn KbdPeek
VIO		VioGetBuf VioGetConfig VioGetCurPos VioGetCurType VioGetPhysBuf VioReadCellStr VioReadCharStr VioScrollUp VioScrollDn VioScrollLf VioScrollRt VioScrUnLock VioSetCurPos VioSetCurType VioSetMode VioGetMode VioShowBuf VioWrtCellStr VioWrtCharStr VioWrtCharStrAtt VioWrtNAttr VioWrtNCell VioWrtNChar VioWrtTTY VioScrLock VioPopUp
Tools		BIND
Modules		DOSCALLS.DLL VIOCALLS.DLL KBDCALLS.DLL MSG.DLL
Libraries		API.LIB OS2386.LIB FAPI.LIB DOSCALLS.LIB SUBCALLS.LIB

2018/08/25 15:05 · prokushev · 0 Comments

From: <https://cocorico.osfree.org/doku/> - **osFree wiki**

Permanent link: <https://cocorico.osfree.org/doku/doku.php?id=en:docs:fapi:mousetscalefact>

Last update: **2021/11/04 13:13**

