



This is part of **Family API** which allow to create dual-os version of program runs under OS/2 and DOS

**Note:** This is legacy API call. It is recommended to use 32-bit equivalent

2021/09/17 04:47 · prokushev · [0 Comments](#)

2021/08/20 03:18 · prokushev · [0 Comments](#)

## DosInsMessage

This call inserts variable text string information into the body of a message. This is useful when messages are loaded before insertion text strings are known.

### Syntax

```
DosInsMessage (IvTable, IvCount, MsgInput, MsgInLength, DataArea,
DataLength,MsgLength)
```

### Parameters

- IvTable ([PCHAR](#) FAR \*) - input : List of double-word pointers. Each pointer points to an ASCIIZ or null terminated DBCS string (variable insertion text). 0 to 9 strings can be present.
- IvCount ([USHORT](#)) - input : 0-9 is the count of variable insertion text strings. If IvCount is 0, IvTable is ignored.
- MsgInput ([PSZ](#)) - input : Address of the input message.
- MsgInLength ([USHORT](#)) - input : Length, in bytes, of the input message.
- DataArea ([PCHAR](#)) - output : Address of the user storage that returns the updated message. If the message is too long to fit in the caller's buffer, as much of the message text as possible is returned with the appropriate return code.
- DataLength ([USHORT](#)) - input : Length, in bytes, of the user's storage area.
- MsgLength ([PUSHORT](#)) - output : Address of the length, in bytes, of the updated message.

### Return Code

rc ([USHORT](#)) - return

Return code descriptions are:

- 0 NO\_ERROR
- 316 ERROR\_MR\_MSG\_TOO\_LONG
- 320 ERROR\_MR\_INV\_IVCOUNT

## Remarks

DosInsMessage returns an error indicating that IvCount is out of range when IvCount is greater than 9. A default message is also placed in the caller's buffer. Refer to [DosGetMessage](#) for details on the default messages. If the numeric value of x in the %x sequence for %1through%9 is less than or equal to IvCount, then text insertion, by substitution for %x, is performed for all occurrences of %x in the body of the message. Otherwise text insertion is ignored and the %x sequence is returned unchanged in the message. Text insertion is performed for all text strings defined by IvCount and IvTable.

Variable data insertion does not depend on a blank character delimiter nor are blanks automatically inserted.

## Example Code

### C Binding

```
#define INCL_DOSMISC

USHORT  rc = DosInsMessage(IvTable, IvCount, MsgInput, MsgInLength,
                          DataArea, DataLength, MsgLength);

PCHAR FAR *   IvTable;      /* Table of variables to insert */
USHORT        IvCount;      /* Number of variables */
PSZ           MsgInput;     /* Address of input message */
USHORT        MsgInLength;  /* Length of input message */
PCHAR         DataArea;     /* Updated message (returned) */
USHORT        DataLength;   /* Length of updated message buffer */
PUSHORT       MsgLength;    /* Length of updated message (returned) */

USHORT        rc;           /* return code */
```

### MASM Binding

```
EXTRN  DosInsMessage:FAR
INCL_DOSMISC      EQU 1

PUSH@  OTHER    IvTable      ;Table of variables to insert
PUSH   WORD     IvCount      ;Number of variables
PUSH@  ASCIIIZ  MsgInput     ;Input message string
PUSH   WORD     MsgInLength   ;Length of input message
PUSH@  OTHER    DataArea     ;Updated message (returned)
PUSH   WORD     DataLength    ;Length of updated message buffer
PUSH@  WORD     MsgLength    ;Length of updated message (returned)
CALL   DosInsMessage
```

Returns WORD

## Note

Text based on <http://www.edm2.com/index.php/DosInsMessage>

| Family API |                 |                                                                                                                                                                                                                                                                                                                                                                              |
|------------|-----------------|------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| DOS        | Process Manager | DosBeep DosExit DosSleep DosExecPgm                                                                                                                                                                                                                                                                                                                                          |
|            | File Manager    | DosChDir DosChgFilePtr DosClose DosDelete DosDupHandle DosMkDir DosMove DosQCurDir DosQCurDisk DosSetFileMode DosOpen DosQFileInfo DosRead DosQFileMode DosQFSInfo DosQVerify DosRmDir DosSelectDisk DosFindClose DosFindFirst DosFindNext DosSetFileInfo DosSetVerify DosWrite DosFileLocks DosSetFHandState DosNewSize DosBufReset DosQFHandState DosSetFSinfo DosShutdown |
|            | Memory Manager  | DosFreeSeg DosSubAlloc DosSubFree DosSubSet DosAllocHuge DosAllocSeg DosReallocHuge DosReallocSeg DosGetHugeShift DosCreateCSAlias                                                                                                                                                                                                                                           |
|            | NLS             | DosCaseMap DosGetCtryInfo DosGetDBCSEv DosSetCtryCode DosGetCollate DosGetMessage DosInsMessage DosPutMessage                                                                                                                                                                                                                                                                |
|            | Date and Time   | DosSetDateTime DosGetDateTime                                                                                                                                                                                                                                                                                                                                                |
|            | Devices         | DosDevConfig DosDevIOctl DosDevIOctl2                                                                                                                                                                                                                                                                                                                                        |
|            | Signals         | DosHoldSignal DosSetSigHandler                                                                                                                                                                                                                                                                                                                                               |
|            | Misc            | BadDynLink DosGetEnv DosGetMachineMode DosGetVersion DosError DosErrClass DosSetVec                                                                                                                                                                                                                                                                                          |
| KBD        |                 | KbdCharIn KbdFlushBuffer KbdGetStatus KbdSetStatus KbdStringIn KbdPeek                                                                                                                                                                                                                                                                                                       |
| VIO        |                 | VioGetBuf VioGetConfig VioGetCurPos VioGetCurType VioGetPhysBuf VioReadCellStr VioReadCharStr VioScrollUp VioScrollDn VioScrollLf VioScrollRt VioScrUnLock VioSetCurPos VioSetCurType VioSetMode VioGetMode VioShowBuf VioWrtCellStr VioWrtCharStr VioWrtCharStrAtt VioWrtNAttr VioWrtNCell VioWrtNChar VioWrtTTY VioScrLock VioPopUp                                        |
| Tools      |                 | BIND                                                                                                                                                                                                                                                                                                                                                                         |
| Modules    |                 | DOSCALLS.DLL VIOCALLS.DLL KBDSCALLS.DLL MSG.DLL                                                                                                                                                                                                                                                                                                                              |
| Libraries  |                 | API.LIB OS2386.LIB FAPI.LIB DOSCALLS.LIB SUBCALLS.LIB                                                                                                                                                                                                                                                                                                                        |

2018/08/25 15:05 · prokushev · 0 Comments

From:

<http://osfree.su/doku/> - **osFree wiki**

Permanent link:

<http://osfree.su/doku/doku.php?id=en:docs:fapi:dosinsmessage>

Last update: **2021/12/05 10:01**

