 This is part of **Family API** which allow to create dual-os version of program runs under OS/2 and DOS

Note: This is legacy API call. It is recommended to use 32-bit equivalent

2021/09/17 04:47 · prokushev · 0 Comments
2021/08/20 03:18 · prokushev · 0 Comments

DosGetMachineMode

This call returns the current mode of the processor, whether the processor is running in the DOS mode or the OS/2 mode. This allows an application to determine whether a dynamic link call is valid or not.

Syntax

```
DosGetMachineMode (MachineMode)
```

Parameters

- MachineMode (PBYTE) - output: Address of the value to indicate the current processor mode. This value may be:
  - 0 - DOS (real) mode
  - 1 - OS/2 (protected) mode.

Return Code

- rc (USHORT) - return

Return code description is:

- 0 NO_ERROR

Remarks

All dynamic link calls are available to an application if the MachineMode value indicates the program is in OS/2 mode. This method provides a self-tailoring application that allows the application to adapt to the execution environment by limiting or enhancing the functions it provides.

If the MachineMode value indicates the program is in DOS mode (or real), the application is limited to a subset of dynamic link calls listed in the Family API.

Example Code

C Binding

```
#define INCL_DOSMISC

USHORT  rc = DosGetMachineMode(MachineMode);
PBYTE   MachineMode;   /* Processor mode (returned) */
USHORT  rc;            /* return code /*/
```

MASM Binding

```
EXTRN  DosGetMachineMode:FAR
INCL_DOSMISC      EQU 1

PUSH@  BYTE    MachineMode   ;Processor mode (returned)
CALL   DosGetMachineMode
```

Returns WORD

Note

Text based on http://www.edm2.com/index.php/DosGetMachineMode

OS/2 API		
DOS	Process Manager	DosBeep DosExit DosSleep DosExecPgm
	File Manager	DosChDir DosChgFilePtr DosClose DosDelete DosDupHandle DosMkDir DosMove DosQCurDir dos16qcurdisk DosSetFileMode DosOpen DosQFileInfo DosRead DosQFileMode DosQFSInfo DosQVerify DosRmDir DosSelectDisk DosFindClose DosFindFirst DosFindNext DosSetFileInfo DosSetVerify DosWrite DosFileLocks DosSetFHandState DosNewSize DosBufReset DosQFHandState DosSetFSinfo
	Memory Manager	DosFreeSeg DosSubAlloc DosSubFree DosSubSet DosAllocHuge DosAllocSeg DosReallocHuge DosReallocSeg DosGetHugeShift DosCreateCSAlias
	NLS	DosCaseMap DosGetCtryInfo DosGetDBCSEv DosSetCtryCode DosGetCollate
	Date and Time	DosSetDateTime DosGetDateTime
	Devices	DosDevConfig DosDevIOCtl
	Signals	DosHoldSignal DosSetSigHandler
	Misc	DosGetEnv DosGetMachineMode DosGetMessage DosGetVersion DosInsMessage DosPutMessage DosError DosErrClass DosSetVec

OS/2 API		
Keyboard Router		KbdCharIn KbdFlushBuffer KbdGetStatus KbdSetStatus KbdStringIn KbdPeek
Video Router		VioGetBuf VioGetCurPos VioGetCurType VioGetPhysBuf VioReadCellStr VioReadCharStr VioScrollDn VioScrollLf VioScrollRt VioScrUnLock VioSetCurPos VioSetCurType VioSetMode VioShowBuf VioWrtCellStr VioWrtCharStr VioWrtCharStrAtt VioWrtNAttr VioWrtNCell VioWrtNChar VioWrtTTY VioScrLock VioGetCP
Mouse Router		
Presentation Manager		
Workplace Shell		
REXX		
MMIO/2		
Tools		
Modules		Modules list
Libraries		DOSCALLS.LIB OS2.LIB PMMLE.LIB REXX.LIB RXSTRING.LIB OS2286.LIB OS2386.LIB PMBIND.LIB

2018/09/05 06:19 · prokushev · 0 Comments

Family API		
DOS	Process Manager	DosBeep DosExit DosSleep DosExecPgm
	File Manager	DosChDir DosChgFilePtr DosClose DosDelete DosDupHandle DosMkDir DosMove DosQCurDir DosQCurDisk DosSetFileMode DosOpen DosQFileInfo DosRead DosQFileMode DosQFSInfo DosQVerify DosRmDir DosSelectDisk DosFindClose DosFindFirst DosFindNext DosSetFileInfo DosSetVerify DosWrite DosFileLocks DosSetFHandState DosNewSize DosBufReset DosQFHandState DosSetFSinfo DosShutdown
	Memory Manager	DosFreeSeg DosSubAlloc DosSubFree DosSubSet DosAllocHuge DosAllocSeg DosReallocHuge DosReallocSeg DosGetHugeShift DosCreateCSAlias
	NLS	DosCaseMap DosGetCtryInfo DosGetDBCSEv DosSetCtryCode DosGetCollate DosGetMessage DosInsMessage DosPutMessage
	Date and Time	DosSetDateTime DosGetDateTime
	Devices	DosDevConfig DosDevIOCtl DosDevIOCtl2
	Signals	DosHoldSignal DosSetSigHandler
	Misc	BadDynLink DosGetEnv DosGetMachineMode DosGetVersion DosError DosErrClass DosSetVec
KBD		KbdCharIn KbdFlushBuffer KbdGetStatus KbdSetStatus KbdStringIn KbdPeek
VIO		VioGetBuf VioGetConfig VioGetCurPos VioGetCurType VioGetPhysBuf VioReadCellStr VioReadCharStr VioScrollUp VioScrollDn VioScrollLf VioScrollRt VioScrUnLock VioSetCurPos VioSetCurType VioSetMode VioGetMode VioShowBuf VioWrtCellStr VioWrtCharStr VioWrtCharStrAtt VioWrtNAttr VioWrtNCell VioWrtNChar VioWrtTTY VioScrLock VioPopUp
Tools		BIND
Modules		DOSCALLS.DLL VIOCALLS.DLL KBDCALLS.DLL MSG.DLL
Libraries		API.LIB OS2386.LIB FAPI.LIB DOSCALLS.LIB SUBCALLS.LIB

2018/08/25 15:05 · prokushev · 0 Comments

From:
https://osfree.ru/doku/ - **osFree wiki**

Permanent link:
https://osfree.ru/doku/doku.php?id=en:docs:fapi:dosgetmachinemode&rev=1629431188

Last update: **2021/08/20 03:46**