



Please help to find info about enries marked as *No info*

BVSCALLS

This is forwarder DLL to [DOSCALLS.DLL](#)


| Ordinal | Name | Desc | Status |
|---------|-------------------|---------------------------|--------|
| 1 | BVSGETPTRDRAWNAME | Forwarder to DOSCALLS.847 | Done |
| 3 | BVSMMAIN | Forwarder to DOSCALLS.845 | Done |
| 4 | BVSREDRAWSIZE | Forwarder to DOSCALLS.846 | Done |


BVSMMAIN functions number

| Number | Name |
|--------|------------------|
| 0 | VioGetPhysBuf |
| 1 | VioGetBuf |
| 2 | VioShowBuf |
| 3 | VioGetCurPos |
| 4 | VioGetCurType |
| 5 | VioGetMode |
| 6 | VioSetCurPos |
| 7 | VioSetCurType |
| 8 | VioSetMode |
| 9 | VioReadCharStr |
| 10 | VioReadCellStr |
| 11 | VioWrtNChar |
| 12 | VioWrtNAttr |
| 13 | VioWrtNCell |
| 14 | VioWrtCharStr |
| 15 | VioWrtCharStrAtt |
| 16 | VioWrtCellStr |
| 17 | VioWrtTTY |
| 18 | VioScrollUp |
| 19 | VioScrollDn |
| 20 | VioScrollLf |
| 21 | VioScrollRt |
| 22 | VioSetAnsi |
| 23 | VioGetAnsi |
| 24 | VioPrtSc |
| 25 | VioScrLock |
| 26 | VioScrUnLock |
| 27 | VioSavRedrawWait |
| 28 | VioSavRedrawUndo |
| 29 | VioPopUp |

| Number | Name |
|--------|----------------|
| 30 | VioEndPopUp |
| 31 | VioPrtScToggle |
| 32 | VioModeWait |
| 33 | VioModeUndo |
| 34 | VioGetFont |
| 35 | VioGetConfig |
| 36 | VioSetCp |
| 37 | VioGetCp |
| 38 | VioSetFont |
| 39 | VioGetState |
| 40 | VioSetState |

| OS/2 DLLs | |
|---|---|
| Base API | DOSCALLS EMXWRAP SUB32 ANSICALL NLS MSG MONCALLS KBDCALLS MOUCALLS VIOCALLS SESMGR BKSCALLS BMSCALLS BVSCALLS NAMPIPES QUECALLS OS2CHAR |
| Bidirectional NLS | BDCALLS BDCALLS32 BDIME BDBVH BDVIEW BDWPCLS BIDIPM PMBIDI |
| Unicode API | UCONV UNIKBD LIBUNI |
| BVH (Base Video Handlers) | BVHINIT BVHMPA BVHVGA BVHSVGA BVHWNDW |
| GRADD subsystem | VMAN SOFTDRAW GRE2VMAN GENGRADD |
| IPF (Information Presentation facility) | HELPMGR HPMGRMRI MINXOBJ IBMHMGR NEWVIEW MINXMRI ERRTXT |
| REXX | REXX REXXAPI REXXUTIL REGINA |
| The core PM DLL's | PMMERGE PMMRGRES PMSHAPI PMSHLTKT PMGRE PMGPI PMDRAG PMCTLS PMMLE PMSPL PMVIOP PMWIN |
| Open32 | PMWINX MIRRORS REGISTRY |
| Intelligent Font Interface drivers | PMATM TRUETYPE PMUNIF FREETYPE PMPRE |
| Data Exchange | PMCLIP PMDDE PMDDEML |
| VDM PM interface | PMVDMH PMVDMP SEAMLESS SHIELD |
| WPS | PMWP PMWPMRU PMVDDROP |
| Miscellaneous | PMPIC PMTKT MVDM |
| SOM API | SOM SOMC |





2016/07/25 02:16 · prokushev · 0 Comments

From: <http://yf2xankbjprn7xs2pd67xix7idfqyxbbl2zul3dgwln2wwefqjsa.b32.i2p/doku/> - osFree wiki

Permanent link: <http://yf2xankbjprn7xs2pd67xix7idfqyxbbl2zul3dgwln2wwefqjsa.b32.i2p/doku/doku.php?id=en:docs:os2:modules:bvscalls>

Last update: 2021/09/10 02:43

