



SESMGR


This is forwarder DLL to [DOSCALLS.DLL](#)


Ordinal	Name	Desc	Status
1	DosSMSGDoPopup	Forwarder to DOSCALLS.686	Done
2	DosSMSwitch	Forwarder to DOSCALLS.687	Done
3	DosSMServeAppReq	Forwarder to DOSCALLS.688	Done
4	DosGetTimes	Forwarder to DOSCALLS.689	Done
5	DosSMSetTitle	Forwarder to DOSCALLS.690	Done
6	DosScrUnlock	Forwarder to DOSCALLS.691	Done
7	DosSMDoAppReq	Forwarder to DOSCALLS.692	Done
8	DosStopSession	Forwarder to DOSCALLS.693	Done
9	DosSelectSession	Forwarder to DOSCALLS.694	Done
10	DosScrLock	Forwarder to DOSCALLS.695	Done
11	DosSavRedrawWait	Forwarder to DOSCALLS.696	Done
12	DosSavRedrawUndo	Forwarder to DOSCALLS.697	Done
13	DosSMSGEndPopup	Forwarder to DOSCALLS.698	Done
14	DosSetSession	Forwarder to DOSCALLS.699	Done
15	DosSetMNLockTime	Forwarder to DOSCALLS.700	Done
16	DosModeUndo	Forwarder to DOSCALLS.701	Done
17	DosStartSession	Forwarder to DOSCALLS.702	Done
18	DosSMGetStatus	Forwarder to DOSCALLS.703	Done
19	DosModeWait	Forwarder to DOSCALLS.704	Done
20	DosSMTerminate	Forwarder to DOSCALLS.705	Done
21	DosSMGetAppReq	Forwarder to DOSCALLS.706	Done
23	DosSMInitialize	Forwarder to DOSCALLS.707	Done
24	DosSMStart	Forwarder to DOSCALLS.708	Done
25	DosSMParentSwitch	Forwarder to DOSCALLS.709	Done
26	DosSMPause	Forwarder to DOSCALLS.710	Done
27	DosSMHDEInit	Forwarder to DOSCALLS.711	Done
28	DosSMPMPresent	Forwarder to DOSCALLS.712	Done
29	DosSMRegisterDD	Forwarder to DOSCALLS.713	Done
30	DosSMSysInit	Forwarder to DOSCALLS.855	Done
31	DosSMNotifyDD	Forwarder to DOSCALLS.714	Done
32	DosSMNotifyDD2	Forwarder to DOSCALLS.715	Done
33	DosSMOpenDD	Forwarder to DOSCALLS.716	Done
34	QhKeybdHandle	Forwarder to DOSCALLS.856	Done
35	QhMouseHandle	Forwarder to DOSCALLS.857	Done
36	DosSMSetSessionType	Forwarder to DOSCALLS.717	Done
37	DosStartSession2	Forwarder to DOSCALLS.669	Done
38	DosSelectSession2	Forwarder to DOSCALLS.670	Done
39	DosSetSession2	Forwarder to DOSCALLS.671	Done

Ordinal	Name	Desc	Status
40	DosStopSession2	Forwarder to DOSCALLS.672	Done
41	DosRegisterNotification	Forwarder to DOSCALLS.673	Done

DosSMRealPrtSc.22 is absent in latest OS/2 DLLs

OS/2 DLLs	
Base API	DOSCALLS EMXWRAP SUB32 ANSICALL NLS MSG MONCALLS KBDSCALLS MOUCALLS VIOCALLS SESMGR BKSCALLS BMSCALLS BVSCALLS NAMPIPES QUECALLS OS2CHAR
Bidirectional NLS	BDCALLS BDCALLS32 BDIME BDBVH BDVIEW BDWPCLS BIDIPM PMBIDI
Unicode API	UCONV UNIKBD LIBUNI
BVH (Base Video Handlers)	BVHINIT BVHMPA BVHVGGA BVHVSVA BVHWNDW
GRADD subsystem	VMAN SOFTDRAW GRE2VMAN GENGRADD
IPF (Information Presentation facility)	HELPMGR HPMGRMRI MINXOBJ IBMHMGR NEWVIEW MINXMRI ERRTXT
REXX	REXX REXXAPI REXXUTIL REGINA
The core PM DLL's	PMMERGE PMMRGRES PMSHAPI PMSHLTKT PMGRE PMGPI PMDRAG PMCTLS PMMLE PMSPL PMVIOP PMWIN
Open32	PMWINX MIRRORS REGISTRY
Intelligent Font Interface drivers	PMATM TRUETYPE PMUNIF FREETYPE PMPRE
Data Exchange	PMCLIP PMDDE PMDDEML
VDM PM interface	PMVDMH PMVDMP SEAMLESS SHIELD
WPS	PMWP PMWPMRU PMVDDROP
Miscellaneous	PMPIC PMTKT MVDM
SOM API	SOM SOMC





2016/07/25 02:16 · prokushev · 0 Comments

From: <http://yf2xankbjprn7xs2pd67xix7idfqyxbbl2zul3dgwln2wwefqjsa.b32.i2p/doku/> - osFree wiki

Permanent link: <http://yf2xankbjprn7xs2pd67xix7idfqyxbbl2zul3dgwln2wwefqjsa.b32.i2p/doku/doku.php?id=en:docs:os2:modules:sesmgr>

Last update: 2018/08/11 16:23

