



FDosSelectDisk

This call selects the drive specified as the default drive for the calling process.

Syntax

DosSelectDisk (DriveNumber)

Parameters

- DriveNumber (USHORT) - input : New default drive number, where 1 = A and 2 = B and so on.

Return Code

```
rc (USHORT) - return
```

Return code descriptions are:

- 0 NO_ERROR
- 15 ERROR_INVALID_DRIVE

Example Code

C Binding

```
#define INCL_DOSFILEMGR

USHORT rc = DosSelectDisk(DriveNumber);
USHORT DriveNumber; /* Default drive number */
USHORT rc; /* return code */
```

MASM Binding

```
EXTRN DosSelectDisk:FAR
INCL_DOSFILEMGR EQU 1

PUSH WORD DriveNumber ;Default drive number
CALL DosSelectDisk
```

Returns WORD

Note

Text based on <http://www.edm2.com/index.php/DosSelectDisk>

| Family API | | |
|------------|---------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| DOS | Process Manager | DosBeep DosExit DosSleep DosExecPgm |
| | File Manager | DosChDir DosChgFilePtr DosClose DosDelete DosDupHandle DosMkDir DosMove DosQCurDir DosQCurDisk DosSetFileMode DosOpen DosQFileInfo DosRead DosQFileMode DosQFSInfo DosQVerify DosRmDir DosSelectDisk DosFindClose DosFindFirst DosFindNext DosSetFileInfo DosSetVerify DosWrite DosFileLocks DosSetFHandState DosNewSize DosBufReset DosQFHandState DosSetFSInfo DosShutdown |
| | Memory Manager | DosFreeSeg DosSubAlloc DosSubFree DosSubSet DosAllocHuge DosAllocSeg DosReallocHuge DosReallocSeg DosGetHugeShift DosCreateCSAlias |
| | NLS | DosCaseMap DosGetCtryInfo DosGetDBCSEv DosSetCtryCode DosGetCollate DosGetMessage DosInsMessage DosPutMessage |
| | Date and Time | DosSetDateTime DosGetDateTime |
| | Devices | DosDevConfig DosDevIOctI DosDevIOctI2 |
| | Signals | DosHoldSignal DosSetSigHandler |
| | Misc | BadDynLink DosGetEnv DosGetMachineMode DosGetVersion DosError DosErrClass DosSetVec |
| KBD | KbdCharIn KbdFlushBuffer KbdGetStatus KbdSetStatus KbdStringIn KbdPeek | |
| VIO | VioGetBuf VioGetConfig VioGetCurPos VioGetCurType VioGetPhysBuf VioReadCellStr VioReadCharStr VioScrollUp VioScrollDn VioScrollLf VioScrollRt VioScrUnLock VioSetCurPos VioSetCurType VioSetMode VioGetMode VioShowBuf VioWrtCellStr VioWrtCharStr VioWrtCharStrAtt VioWrtNAttr VioWrtNCell VioWrtNChar VioWrtTTY VioScrLock VioPopUp | |
| Tools | BIND | |
| Modules | DOSCALLS.DLL VIOCALLS.DLL KBDCALLS.DLL MSG.DLL | |
| Libraries | API.LIB OS2386.LIB FAPI.LIB DOSCALLS.LIB SUBCALLS.LIB | |

2018/08/25 15:05 · prokushev · 0 Comments

From: <http://osfree.ru/doku/> - **osFree wiki**

Permanent link: <http://osfree.ru/doku/doku.php?id=en:docs:fapi:dosselectdisk&rev=1535865760>

Last update: **2018/09/02 05:22**

