 This is part of **Family API** which allow to create dual-os version of program runs under OS/2 and DOS

Note: This is legacy API call. It is recommended to use 32-bit equivalent

2021/09/17 04:47 · prokushev · 0 Comments
2021/08/20 03:18 · prokushev · 0 Comments

DosInsMessage

This call inserts variable text string information into the body of a message. This is useful when messages are loaded before insertion text strings are known.

Syntax

```
DosInsMessage (IvTable, IvCount, MsgInput, MsgInLength, DataArea,
DataLength,MsgLength)
```

Parameters

- IvTable (PCHAR FAR *) - input : List of double-word pointers. Each pointer points to an ASCIIZ or null terminated DBCS string (variable insertion text). 0 to 9 strings can be present.
- IvCount (USHORT) - input : 0-9 is the count of variable insertion text strings. If IvCount is 0, IvTable is ignored.
- MsgInput (PSZ) - input : Address of the input message.
- MsgInLength (USHORT) - input : Length, in bytes, of the input message.
- DataArea (PCHAR) - output : Address of the user storage that returns the updated message. If the message is too long to fit in the caller's buffer, as much of the message text as possible is returned with the appropriate return code.
- DataLength (USHORT) - input : Length, in bytes, of the user's storage area.
- MsgLength (PUSHORT) - output : Address of the length, in bytes, of the updated message.

Return Code

rc (USHORT) - return

Return code descriptions are:

- 0 NO_ERROR
- 316 ERROR_MR_MSG_TOO_LONG
- 320 ERROR_MR_INV_IVCOUNT

Remarks

DosInsMessage returns an error indicating that IvCount is out of range when IvCount is greater than 9. A default message is also placed in the caller's buffer. Refer to DosGetMessage for details on the default messages. If the numeric value of x in the %x sequence for %1through%9 is less than or equal to IvCount, then text insertion, by substitution for %x, is performed for all occurrences of %x in the body of the message. Otherwise text insertion is ignored and the %x sequence is returned unchanged in the message. Text insertion is performed for all text strings defined by IvCount and IvTable.

Variable data insertion does not depend on a blank character delimiter nor are blanks automatically inserted.

Example Code

C Binding

```
#define INCL_DOSMISC

USHORT  rc = DosInsMessage(IvTable, IvCount, MsgInput, MsgInLength,
                           DataArea, DataLength, MsgLength);

PCHAR FAR *      IvTable;       /* Table of variables to insert */
USHORT           IvCount;       /* Number of variables */
PSZ              MsgInput;      /* Address of input message */
USHORT           MsgInLength;   /* Length of input message */
PCHAR            DataArea;      /* Updated message (returned) */
USHORT           DataLength;    /* Length of updated message buffer */
PUSHORT          MsgLength;     /* Length of updated message (returned) */

USHORT           rc;            /* return code */
```

MASM Binding

```
EXTRN  DosInsMessage:FAR
INCL_DOSMISC      EQU 1

PUSH@  OTHER   IvTable       ;Table of variables to insert
PUSH   WORD    IvCount       ;Number of variables
PUSH@  ASCIIZ  MsgInput      ;Input message string
PUSH   WORD    MsgInLength   ;Length of input message
PUSH@  OTHER   DataArea      ;Updated message (returned)
PUSH   WORD    DataLength    ;Length of updated message buffer
PUSH@  WORD    MsgLength     ;Length of updated message (returned)
CALL   DosInsMessage
```

Returns WORD

Note

Text based on http://www.edm2.com/index.php/DosInsMessage

Family API		
DOS	Process Manager	DosBeep DosExit DosSleep DosExecPgm
	File Manager	DosChDir DosChgFilePtr DosClose DosDelete DosDupHandle DosMkDir DosMove DosQCurDir DosQCurDisk DosSetFileMode DosOpen DosQFileInfo DosRead DosQFileMode DosQFSInfo DosQVerify DosRmDir DosSelectDisk DosFindClose DosFindFirst DosFindNext DosSetFileInfo DosSetVerify DosWrite DosFileLocks DosSetFHandState DosNewSize DosBufReset DosQFHandState DosSetFSinfo DosShutdown
	Memory Manager	DosFreeSeg DosSubAlloc DosSubFree DosSubSet DosAllocHuge DosAllocSeg DosReallocHuge DosReallocSeg DosGetHugeShift DosCreateCSAlias
	NLS	DosCaseMap DosGetCtryInfo DosGetDBCSEv DosSetCtryCode DosGetCollate DosGetMessage DosInsMessage DosPutMessage
	Date and Time	DosSetDateTime DosGetDateTime
	Devices	DosDevConfig DosDevIOCtl DosDevIOCtl2
	Signals	DosHoldSignal DosSetSigHandler
	Misc	BadDynLink DosGetEnv DosGetMachineMode DosGetVersion DosError DosErrClass DosSetVec
KBD		KbdCharIn KbdFlushBuffer KbdGetStatus KbdSetStatus KbdStringIn KbdPeek
VIO		VioGetBuf VioGetConfig VioGetCurPos VioGetCurType VioGetPhysBuf VioReadCellStr VioReadCharStr VioScrollUp VioScrollDn VioScrollLf VioScrollRt VioScrUnLock VioSetCurPos VioSetCurType VioSetMode VioGetMode VioShowBuf VioWrtCellStr VioWrtCharStr VioWrtCharStrAtt VioWrtNAttr VioWrtNCell VioWrtNChar VioWrtTTY VioScrLock VioPopUp
Tools		BIND
Modules		DOSCALLS.DLL VIOCALLS.DLL KBDCALLS.DLL MSG.DLL
Libraries		API.LIB OS2386.LIB FAPI.LIB DOSCALLS.LIB SUBCALLS.LIB

2018/08/25 15:05 · prokushev · 0 Comments

From:
http://osfree.org/doku/ - **osFree wiki**

Permanent link:
http://osfree.org/doku/doku.php?id=en:docs:fapi:dosinsmessage

Last update: **2021/12/05 10:01**