MouGetDevStatus

Bindings: C, MASM

This call returns status flags for the installed mouse device driver.

MouGetDevStatus (DeviceStatus, DeviceHandle)

DeviceStatus (**PUSHORT**) - output Address of the current status flag settings for the installed mouse device driver.

The return value is a 2-byte set of bit flags.

Bit	Description
15-10	Reserved, set to zero.
9	Set if mouse data returned in mickeys, not pels.
8	Set if the drawing operations for pointer draw routine are disabled.
7-4	Reserved, set to zero.
3	Set if pointer draw routine disabled by unsupported mode.
2	Set if flush in progress.
1	Set if block read in progress.
0	Set if event queue busy with I/O.

DeviceHandle (**HMOU**) - input Mouse device handle from a previous MouOpen.

rc (**USHORT**) - return Return code descriptions are:

0	NO_ERROR
385	ERROR_MOUSE_NO_DEVICE
466	ERROR_MOU_DETACHED
501	ERROR_MOUSE_NO_CONSOLE
505	ERROR_MOU_EXTENDED_SG

C bindings

```
#define INCL_MOU

USHORT  rc = MouGetDevStatus(DeviceStatus, DeviceHandle);

PUSHORT          DeviceStatus;  /* Current status flags */
HMOU             DeviceHandle;  /* Mouse device handle */

USHORT           rc;            /* return code */
```

MASM bindings

```
EXTRN  MouGetDevStatus:FAR
INCL_MOU            EQU 1
```

```
PUSH@  WORD    DeviceStatus  ;Current status flags
PUSH   WORD    DeviceHandle  ;Mouse device handle
CALL   MouGetDevStatus

Returns WORD
```

From:
https://cocorico.osfree.org/doku/ - **osFree wiki**

Permanent link:
https://cocorico.osfree.org/doku/doku.php?id=en:ibm:prcp:mou:getdevstatus

Last update: **2016/09/15 03:41**